

# AIM Lid-Driven Cavity - Mesh

Author(s): Sebastian Vecchi, ANSYS Inc.

[Problem Specification](#)

[1. Pre-Analysis & Start-Up](#)

[2. Geometry](#)

[3. Mesh](#)

[4. Physics Setup](#)

[5. Results](#)

[6. Verification & Validation](#)

## Mesh

Close the **Model Editor**, then click on **Mesh** in the workflow.

### Set Mesh Size & Controls

Retain the default mesh settings. AIM will prompt the user to fix the boundary layer before generating the mesh. [Click on Boundary Layer under Mesh Controls.](#) Select the faces of the flow volume.

### Generate Mesh

Return to the **Mesh** task and click **Generate Mesh** under **Output** or at the top of the Mesh panel. AIM should detect that you are ready to generate the mesh and highlight the buttons in blue.

[Go to Step 4: Physics Set-Up](#)

[Go to all ANSYS AIM Learning Modules](#)